

The screenshot shows the 'Status' page of the EE11 device. The left sidebar contains navigation options: STATUS, SYSTEM SETTINGS, SERIAL PORT SETTINGS, COMMUNICATION SETTINGS, ADVANCED SETTINGS, and OTHERS. The main content area is titled 'Status' and 'System running status overview'. It features two main sections: 'System State' and 'Serial Port State'. The 'System State' section includes fields for Product Name (EE11), MAC (98D863D38AE2), DHCP (Enable), Subnet Mask (255.255.255.0), DNS (223.5.5.5), System Time (NTP Disabled), Remaining RAM (23500), and Configuration Protected (Disable). The 'Serial Port State' section includes Received Bytes (0), Sent Bytes (0), Failed Bytes (0), Received Frames (0), Sent Frames (0), and Failed Frames (0). A 'Helper' button is visible on the right side of the page.

| System State            |                    |
|-------------------------|--------------------|
| Product Name            | MAC                |
| EE11                    | 98D863D38AE2       |
| DHCP                    | IP                 |
| Enable                  | 192.168.178.55     |
| Subnet Mask             | Gateway            |
| 255.255.255.0           | 192.168.178.1      |
| DNS                     | Firmware Version   |
| 223.5.5.5               | 1.34.9             |
| System Time             | Total Running Time |
| NTP Disabled            | 0-Day 3:46:22      |
| Remaining RAM           | Max Block Size     |
| 23500                   | 18684              |
| Configuration Protected |                    |
| Disable                 |                    |

| Serial Port State |                 |
|-------------------|-----------------|
| Received Bytes    | Received Frames |
| 0                 | 0               |
| Sent Bytes        | Sent Frames     |
| 0                 | 0               |
| Failed Bytes      | Failed Frames   |
| 0                 | 0               |
| Config            |                 |
| 9600,8,1,NONE     |                 |

This screenshot shows the 'Communication State' section of the EE11 status page. The left sidebar is the same as in the previous screenshot. The main content area now displays the 'Communication State - netp' section, which includes Received Bytes (0), Sent Bytes (0), Failed Bytes (0), Received Frames (0), Sent Frames (0), Failed Frames (0), Protocol (TCP-SERVER), and State (Server Created). The 'Helper' button on the right now shows 'Current System Time'. The footer of the page contains the build number 'build1910161405054826' and a recommendation to use Google Chrome, Mozilla Firefox, or Internet Explorer 11+.

| Communication State - 'netp' |                 |
|------------------------------|-----------------|
| Received Bytes               | Received Frames |
| 0                            | 0               |
| Sent Bytes                   | Sent Frames     |
| 0                            | 0               |
| Failed Bytes                 | Failed Frames   |
| 0                            | 0               |
| Protocol                     | State           |
| TCP-SERVER                   | Server Created  |
| IP                           |                 |

build1910161405054826  
Recommend using Google Chrome, Mozilla Firefox, Internet Explorer 11+

File Bearbeiten Ansicht Chronik Lesezeichen Extras Hilfe

EE11 x DKB - Deutsche Kreditbank AG x Übersetzer - Google Suche x +

192.168.178.55/system.html 80% übersetzer

### System Settings

Change the device system settings

**Authentication**

User Name: admin  
Password: •••••

**Basic Settings**

Host Name: Eport-EE11

**WAN Settings**

DHCP: ON  
DNS: 223.5.5.5

**Telnet Settings**

Enable: ON  
Telnet Port: 23  
Echo: ON

**Web Settings**

Enable: ON  
Web Port: 80

**NTP Settings**

Enable: OFF

Submit Reset

192.168.178.55/system.html

**STATUS**

- SYSTEM SETTINGS
- SERIAL PORT SETTINGS
- COMMUNICATION SETTINGS
- ADVANCED SETTINGS
- OTHERS

**Helper**

System settings

File Bearbeiten Ansicht Chronik Lesezeichen Extras Hilfe

EE11 x DKB - Deutsche Kreditbank AG x Übersetzer - Google Suche x +

192.168.178.55/uart.html 80% übersetzer

### Serial Port Settings

change the device serial port settings

**Basic Settings**

Baud Rate: 9600  
Data Bit: 8  
Stop Bit: 1  
Parity: None

**Buffer Settings**

Buffer Size: 512  
Gap Time: 50

**Flow Control Settings**

Flow Control: Half Duplex

**Cli Settings**

Cli: Serial String  
Serial String: +++  
Waiting Time: 300

**Protocol Settings**

Protocol: Modbus

Submit Reset

192.168.178.55/uart.html

**STATUS**

- SYSTEM SETTINGS
- SERIAL PORT SETTINGS
- COMMUNICATION SETTINGS
- ADVANCED SETTINGS
- OTHERS

**Helper**

Config the serial port

EE11 | DKB - Deutsche Kreditbank AG | Übersetzer - Google Suche | 192.168.178.55/socket.html | 80% | Übersetzer

### Communication Settings

change the device socket settings

netp +Add Helper  
Communication settings

**Basic Settings**

|          |            |
|----------|------------|
| Name     | netp       |
| Protocol | Tcp Server |

**Socket Settings**

|               |      |
|---------------|------|
| Local Port    | 8899 |
| Buffer Size   | 512  |
| Keep Alive(s) | 60   |
| Timeout(s)    | 0    |

**Protocol Settings**

|            |   |
|------------|---|
| Max Accept | 3 |
|------------|---|

**More Settings**

|          |         |
|----------|---------|
| Security | Disable |
| Route    | Uart    |

Submit Delete Reset

192.168.178.55/socket.html | build1910161405054826

EE11 | DKB - Deutsche Kreditbank AG | Übersetzer - Google Suche | 192.168.178.55/others.html | 80% | Übersetzer

### Others

change the device other settings

Helper  
Other settings

**Backup/Restore Configuration**

|         |               |
|---------|---------------|
| Backup  | Backup        |
| Restore | + Choose File |

**Upgrade**

|          |               |
|----------|---------------|
| Firmware | + Choose File |
|----------|---------------|

**Factory Settings**

|       |       |
|-------|-------|
| Set   | Set   |
| Clear | Clear |

**Reload/Restart**

|                |  |
|----------------|--|
| Reload Options | <input type="checkbox"/> SYS <input type="checkbox"/> UART <input type="checkbox"/> SOCK |
| Restart        | Restart  |

build1910161405054826  
Recommend using Google Chrome, Mozilla Firefox, Internet Explorer 11+

192.168.178.55/others.html